


Servisi za otvorenu nauku u jugoistočnoj Evropi

OpenStack FINKI-Cloud

Anastas Mišev

Univerzitet Sv. Kiril i Metodij, Skopje



NIxOS
Europe

Agenda

Šta je FINKI-Cloud?

Osnovne karakteristike

Prednosti

Registracija

Kreiranje virtuelnih mašina

Konfiguracija mreže

Povećanje kapaciteta diskova

Šta je FINKI-Cloud?

- FINKI-Cloud predstavlja IaaS rešenje
 - IaaS – Infrastructure as a Service, infrastruktura kao servis
- Omogućava korišćenje računarskih resursa po potrebi, bilo kada.
- Računarski resursi su:
 - Virtuelne mašine
 - Disk prostor
 - Mreža
- Dostupno za šиру naučno-istraživačku zajednicu.

Karakteristike

Brzo

- Podizanje novog resursa traje nekoliko sekundi

Sigurno

- Potpuna izolacija resursa između korisnika

Poznato

- Okoline poznate istraživačima, dostupni najčešće korišćeni operativni sistemi

Lako

- Interakcija sa sistemom odvija se preko grafičkog interfejsa uz pomoć čarobnjaka

Prednosti


- Povećani kvalitet istraživanja – resursu velikog kapaciteta omogućuju obradu većih i kompleksnijih skupova podataka.
 - Povećani kvantitet istraživanja – resursi su odmah dostupni za korišćenje, bez čekanja; savremeni hardver smanjuje vreme proračuna
 - Ekonomično – nema dodatnih investicija ili lokalnih infrastrukturnih instalacija
 - Centralizovano – olakšana saradnja sa ostalim istraživačima i deljenje skupova podataka
-

Preduslovi i proces registracije

- Servis je dostupan na <https://openstack.finki.ukim.mk/>
- Registracija je preko NI4OS AAI korišćenjem akreditiva
 - Vaše institucije, ako je članica eduGAIN-a
 - Korišćenjem socijalnih mreža ili trećih servisa (Facebook, Google, GitHub)
- Posle inicialne registracije, potrebno je da vlasnik resursa potvrdi pristup
 - Brzi povratni odgovor
 - Obnova pristupa svake godine
- Uslovi korišćenja – [FINKI-Cloud Terms of Use](#)


Registracija

□ <https://openstack.finki.ukim.mk/>



Početna stranica

□ Početna stranica – trenutna iskorišćenost resursa



Kreiranje prve virtualne mašine

- ❑ Navigacija do željene stranice preko menija na levoj strani
 - ❑ Project -> Compute -> Instances

The screenshot shows the 'Instances' page within the OpenShift interface. At the top, there's a breadcrumb navigation: Project / Compute / Instances. Below the header, the word 'Instances' is displayed. On the right side of the header, there are search and filter controls: 'Instance ID = ▾', a search input field, a 'Filter' button, and a 'Launch Instance' button with a cloud icon. The main area features a table with the following columns: Instance Name, Image Name, IP Address, Flavor, Key Pair, Status, Availability Zone, Task, Power State, Age, and Actions. A message 'No items to display.' is centered in the table's body.

- ❑ Launch Instance – čarobnjak za podizanje virtuelnih mašina

Čarobnjak za kreiranje virtuelnih mašina – Details

- Više koraka, ali samo nekoliko suštinski važnih

Launch Instance

Details

Please provide the initial hostname for the instance, the availability zone where it will be deployed, and the instance count. Increase the Count to create multiple instances with the same settings.

Instance Name * demo_vm01

Description

Total Instances (10 Max) 10%

0 Current Usage
1 Added
9 Remaining

Source *
Flavor *
Networks *
Network Ports
Security Groups nova
Key Pair
Configuration
Server Groups
Scheduler Hints
Metadata


Count * 1

Cancel Back Next Launch Instance



Čarobnjak za kreiranje virtuelnih mašina – Source

- ❑ Izbor željenog operativnog sistema
 - ❑ Boot Source -> Image
- ❑ Mogućnost dodavanja dodatnog disk prostora koji je moguće priključiti i drugoj virtuelnoj mašini.
 - ❑ Create New Volume – Yes/No



Čarobnjak za kreiranje virtuelnih mašina – Flavor

- Dimenzioniranje virtuelne mašine u zavisnosti od potreba
- Mogućnost izbora osam predefinisanih konfiguracija
- Disk prostor se uvek može proširiti dodatnim volumenima
- U slučaju potrebe može da se izvrši re-dimenzioniranje bez potrebe brisanja i ponovnog kreiranja mašine

Allocated						
Name	VCPUS	RAM	Total Disk	Root Disk	Ephemeral Disk	Public
▶ t2.large	2	8 GB	60 GB	60 GB	0 GB	Yes
▼ Available <small>7</small>						
Select one						
▶ t2.nano	1	512 MB	20 GB	20 GB	0 GB	Yes
▶ t2.micro	1	1 GB	20 GB	20 GB	0 GB	Yes
▶ t2.small	1	2 GB	20 GB	20 GB	0 GB	Yes
▶ t2.medium	2	4 GB	60 GB	60 GB	0 GB	Yes
▶ t2.xlarge	4	16 GB	60 GB	60 GB	0 GB	Yes
▶ c5.4xlarge	16	32 GB	60 GB	60 GB	0 GB	Yes
▶ t2.2xlarge	8	32 GB	60 GB	60 GB	0 GB	Yes

Flavors manage the sizing for the compute, memory and storage capacity of the instance.

◀ Back ▶ Next ▶ Launch Instance

Čarobnjak za kreiranje virtuelnih mašina – Network

- ❑ Izbor mrežne konfiguracije
- ❑ Dostupne su dve mreže, kao i mogućnost definisanja vlastitih
 - ❑ external-3000 – spoljni pristup preko automatski dodeljene javne IP adrese
 - ❑ internet-through-nat – za virtuelne mašine koje ne plasiraju javne sadržaje, dostupne samo interno ili preko druge mašine koja ima i javnu i lokalnu adresu

Networks provide the communication channels for instances in the cloud.

▼ Allocated 1 Select networks from those listed below.

Network	Subnets Associated	Shared	Admin State	Status
external-3000	vlan-3000	Yes	Up	Active


▼ Available 1 Select at least one network

Click here for filters or full text search.

Network	Subnets Associated	Shared	Admin State	Status
internet-through-nat	internet-subnet	Yes	Up	Active


Čarobnjak za kreiranje virtuelnih mašina – Security Groups

- Pravila za dolazni i izlazni saobraćaj ka i od virtuelne mašine
- Jedna predefinisana polisa – spoljašnji pristup nije dozvoljen
- Potrebno je definisati vlastitu (kasnije..)
- Mogućnost promene u realnom vremenu, bez potrebe restartovanja virtuelne mašine



Čarobnjak za kreiranje virtuelnih mašina – Key Pair

- Izbor javnog SSH ključa za pristup mašini
- Mogućnost dodavanja novog, direktno iz čarobnjaka
- Jednom dodani ključ može se koristiti neograničeni broj puta kasnije
- Važno i za Microsoft Windows mašine, učestvuje u definisanju inicijalne lozinke



Pregled kreirane virtuelne mašine

- Posle završetka zadnjeg koraka, virtuelna mašina se pokreće dugmetom „Launch Instance“

Instances											
	Instance Name	Image Name	IP Address	Flavor	Key Pair	Status	Availability Zone	Task	Power State	Age	Actions
<input type="checkbox"/>	demo_vm01	ubuntu-server-18.0	194.149.135.31	t2.large	DemoKey	Build	nova	Spawning	No State	0 minutes	<button>Associate Floating IP</button>
Displaying 1 item											

- Ukoliko je izabrana predefinisana sigurnosna grupa, potrebno je napraviti promenu da bi se moglo pristupiti iz spoljašnje mreže
- Pristup konzoli je preko:
 - Actions -> Console

Omogućavanje spoljašnjeg pristupa (1)

- ❑ Potrebno je omogućiti javni pristup željenim portovima preko
 - ❑ Promene predefinisane sigurnosne polise
 - ❑ Preko definisanja nove sigurnosne polise
- ❑ Project -> Network -> Security Groups

Displaying 1 item				
<input type="checkbox"/>	Name	Security Group ID	Description	Actions
<input type="checkbox"/>	default	44547bd6-6bfd-4f64-87d9-3948049bb014	Default security group	<button>Manage Rules</button>
Displaying 1 item				

Omogućavanje spoljašnjeg pristupa (2)

- Manage Rules -> Add Rule
- Mogućnost izbora iz liste najčešće korišćenih protokola ili definisanje vlastitih pravila

Add Rule

Rule *
SSH

Description
SSH pristap

Remote *
CIDR

CIDR
0.0.0.0/0

Description:
Rules define which traffic is allowed to instances assigned to the security group. A security group rule consists of three main parts:
Rule: You can specify the desired rule template or use custom rules, the options are Custom TCP Rule, Custom UDP Rule, or Custom ICMP Rule.
Open Port/Port Range: For TCP and UDP rules you may choose to open either a single port or a range of ports. Selecting the "Port Range" option will provide you with space to provide both the starting and ending ports for the range. For ICMP rules you instead specify an ICMP type and code in the spaces provided.
Remote: You must specify the source of the traffic to be allowed via this rule. You may do so either in the form of an IP address block (CIDR) or via a source group (Security Group). Selecting a security group as the source will allow any other instance in that security group access to any other instance via this rule.

Cancel Add



Add Rule

Rule *
Custom TCP Rule

Custom TCP Rule
Custom UDP Rule
Custom ICMP Rule
Other Protocol
All ICMP
All TCP
All UDP
DNS
HTTP
HTTPS
IMAP
IMAPS
LDAP
MS SQL
MYSQL
POP3
POP3S
RDP
SMTP
SMTPS
SSH

Description:
Rules define which traffic is allowed to instances assigned to the security group. A security group rule consists of three main parts:
Rule: You can specify the desired rule template or use custom rules, the options are Custom TCP Rule, Custom UDP Rule, or Custom ICMP Rule.
Open Port/Port Range: For TCP and UDP rules you may choose to open either a single port or a range of ports. Selecting the "Port Range" option will provide you with space to provide both the starting and ending ports for the range. For ICMP rules you instead specify an ICMP type and code in the spaces provided.
Remote: You must specify the source of the traffic to be allowed via this rule. You may do so either in the form of an IP address block (CIDR) or via a source group (Security Group). Selecting a security group as the source will allow any other instance in that security group access to any other instance via this rule.

Cancel Add

Pristup virtuelnoj mašini

- ❑ Nakon dodavanja neophodnog pravila, omogućen je pristup mašini preko javne, spoljašnje mreže
- ❑ Inicijalna najava vrši se prek pred-definisanog korisničkog imena koje zavisi od operativnog sistema
 - ❑ Ubuntu -> ubuntu
 - ❑ Debian -> debian
 - ❑ ...
- ❑ IP adresu mašine možete videti u delu za prikaz svih vaših mašina
 - ❑ Project -> Compute -> Instances



Povećanje disk prostora (1)

- ❑ Dopunski disk prostor može da se kreira i doda i bilo kad svakoj virtuelnoj mašini.
- ❑ Project -> Volumes -> Volumes -> Create Volume
- ❑ Izbor tipa diska (SSD ili mehanički) preko *Type*
 - ❑ RBDFAST – SSD diskovi
 - ❑ RBD – mehanički diskovi

The screenshot shows the 'Create Volume' dialog box with the following fields:

- Volume Name:** dataset01
- Description:** (Empty)
- Volume Type Description:** RBD
No description available.
- Volume Limits:** Total Gibibytes: 0 of 1,000 GiB Used
Number of Volumes: 0 of 10 Used
- Volume Source:** No source, empty volume
- Type:** RBD
- Size (GiB) *:** 20
- Availability Zone:** nova
- Group:** No group

At the bottom right are 'Cancel' and 'Create Volume' buttons.

Povećanje disk prostora (2)

- ❑ Povezivanje kreiranog volumena
 - ❑ Project -> Compute -> Instances -> Attach Volume
- ❑ Disk postaje odmah dostupan, nije potrebno restartovanje

The screenshot illustrates the process of attaching a volume to a running instance. It consists of three main parts:

- Top Panel:** A table listing instances. One row is selected for "demo_vm01". The "Actions" column for this row has a dropdown menu open, showing options: Associate Floating IP, Attach Interface, Detach Interface, Edit Instance, and Attach Volume.
- Middle Panel:** A modal window titled "Attach Volume". It contains a "Volume ID" dropdown set to "dataset01 (37932818-4961-45c5-b3b8-0581bf64...)" and a "Description:" field containing the placeholder "Attach Volume to Running Instance.". A large blue arrow points from this window to a terminal window.
- Bottom Panel:** A terminal window showing the output of the "lsblk" command. The output details a new disk: "/dev/vdb: 20 GiB, 21474836480 bytes, 41943040 sectors". A smaller blue arrow points from the terminal window back to the "Attach Volume" modal.

Hvala na pažnji
Pitanja?

